

Downloading of Installation Setup from mFMS Server

1. User provided with VISIONTEK GL11 PoS can install the FMS Application by downloading the "Installation Setup" from "mFMS Site"
2. For this user has to visit "mFMS Site" go to options download GL11 setup file "FMSSetup.zip" from site into local PC
3. This file "FMSSetup.zip" has to unzipped in PC, which will generate 2 files "rootfs_patch.tar.bz2" & "rootfs_update.sh"
4. These 2 files have to be copied into empty/blank pen drive/USB drive of standard makes and of 4/8/16GB memory
5. Then connect the pen drive/USB drive to GL11 POS device and restart the device
6. Once the device start it will identify the files and installs FMS Application
7. Once Application is installed long Beep sound it audible and devices shutdowns
8. Now user can turn on the device and FMS icon is visible on the Desktop Screen of the Device